



Tanium™ Client Management User Guide

Version 1.1.4

June 11, 2020

The information in this document is subject to change without notice. Further, the information provided in this document is provided “as is” and is believed to be accurate, but is presented without any warranty of any kind, express or implied, except as provided in Tanium’s customer sales terms and conditions. Unless so otherwise provided, Tanium assumes no liability whatsoever, and in no event shall Tanium or its suppliers be liable for any indirect, special, consequential, or incidental damages, including without limitation, lost profits or loss or damage to data arising out of the use or inability to use this document, even if Tanium Inc. has been advised of the possibility of such damages.

Any IP addresses used in this document are not intended to be actual addresses. Any examples, command display output, network topology diagrams, and other figures included in this document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

Please visit <https://docs.tanium.com> for the most current Tanium product documentation.

This documentation may provide access to or information about content, products (including hardware and software), and services provided by third parties (“Third Party Items”). With respect to such Third Party Items, Tanium Inc. and its affiliates (i) are not responsible for such items, and expressly disclaim all warranties and liability of any kind related to such Third Party Items and (ii) will not be responsible for any loss, costs, or damages incurred due to your access to or use of such Third Party Items unless expressly set forth otherwise in an applicable agreement between you and Tanium.

Further, this documentation does not require or contemplate the use of or combination with Tanium products with any particular Third Party Items and neither Tanium nor its affiliates shall have any responsibility for any infringement of intellectual property rights caused by any such combination. You, and not Tanium, are responsible for determining that any combination of Third Party Items with Tanium products is appropriate and will not cause infringement of any third party intellectual property rights.

Tanium is committed to the highest accessibility standards to make interaction with Tanium software more intuitive and to accelerate the time to success. To ensure high accessibility standards, Tanium complies with the U.S. Federal regulations - specifically Section 508 of the Rehabilitation Act of 1998. We have conducted third-party accessibility assessments over the course of product development for many years, and most recently a comprehensive audit against the WCAG 2.1 / VPAT 2.3 standards for all major product modules was completed in September 2019. Tanium can make available any VPAT reports on a module-by-module basis as part of a larger solution planning process for any customer or prospect.

As new products and features are continuously delivered, Tanium will conduct testing to identify potential gaps in compliance with accessibility guidelines. Tanium is committed to making best efforts to address any gaps quickly, as is feasible, given the severity of the issue and scope of the changes. These objectives are factored into the ongoing delivery schedule of features and releases with our existing resources.

Tanium welcomes customer input on making solutions accessible based on your Tanium modules and assistive technology requirements. Accessibility requirements are important to the Tanium customer community and we are committed to prioritizing these compliance efforts as part of our overall product roadmap. Tanium maintains transparency on our progress and milestones and welcomes any further questions or discussion around this work. Contact your TAM, sales representative, or email accessibility@tanium.com to make further inquiries.

Tanium is a trademark of Tanium, Inc. in the U.S. and other countries. Third-party trademarks mentioned are the property of their respective owners.

© 2020 Tanium Inc. All rights reserved.

Table of contents

- Client Management overview 7**
- Client deployment 7
- Deployment process overview 7
- Client configurations 7
- Client credentials 7
- Target endpoints 7
- Client health monitoring 8
- Integration with other Tanium products 8
- Discover 8
- Trends 8
- Getting started 9**
- Client Management requirements 10**
- Tanium dependencies 10
- Tanium™ Module Server 10
- Endpoints 11
- Supported operating systems 11
- Account permissions 12
- Windows endpoints 12
- Non-Windows endpoints 12
- Host and network security requirements 12
- Ports 13
- Security exclusions 14
- Internet URLs 17

User role requirements	17
Installing Client Management	29
Before you begin	29
Import and configure Client Management with default settings	29
Import and configure Client Management with custom settings	29
Configure service account	30
Verify installation	30
(Tanium 7.2.x, 7.3.x only) Upload Tanium public key	30
Add client installation files for air-gapped environments	30
What to do next	31
Deploying Tanium Client	32
Plan deployment targeting	32
Prepare for deployment to Linux, macOS, or UNIX endpoints	32
Prepare for deployment to Windows endpoints	33
Configure client settings	34
Configure client credentials	36
Configure a deployment	38
Run and monitor deployments	40
Deployment steps	41
Deployment status	42
Verify client installation	42
Monitoring client health	43
View a summary of client health information	43
View detailed client health information for an endpoint	45
View detailed status information	46

View detailed client settings information	47
View logs from the connected client	49
View action logs from the connected client	49
Disconnect and return to summary information	49
Troubleshooting Client Management	50
Collect logs	50
Download deployment information	50
Troubleshoot deployments	50
Problem: A new deployment instantly switches to the Completed status with no attempted deployments to endpoints	50
Solution	51
Problem: Endpoint Install Status = ERROR_EXISTING_INSTALL	51
Solution	51
Problem: Endpoint Install Status = ERROR_ACQUIRE_LOGS_FAIL	51
Solution	51
Problem: Endpoint Install Status = ERROR_CONNECTION_FAIL	51
Solution	52
Problem: Endpoint Install Status = ERROR_CONNECTION_FAIL	52
Solution	53
Problem: Endpoint Install Status = ERROR_ACQUIRE_LOGS_FAIL	53
Solution	53
Uninstall Client Management	53

Client Management overview

With Client Management, you can rapidly deploy the Tanium™ Client to targeted sets of endpoints. You can also continuously monitor the health of all installed clients to help quickly identify, diagnose, and resolve issues with clients.

Client deployment

Deploy the Tanium™ Client to targeted sets of Windows, Linux, Mac, Solaris, or AIX endpoints.

Deployment process overview

Before you begin the deployment process, determine the set of endpoints that you are going to target. You can target by single IP, computer name, IP or CIDR range, or label that you defined in Tanium™ Discover.

To deploy clients, configure client configurations and credentials. You can then use those configurations to create deployments, which are targeted at specific sets of unmanaged endpoints. The Tanium Module Server installs the Tanium Client on the targeted endpoints. Depending on the results, you can reuse the configurations to try deployments again or target different sets of endpoints.

Client configurations

A client configuration includes client settings specific to a deployment, including the version of the Tanium Client to deploy, and the Tanium Server with which to associate the client. Client configurations can also contain tags, which identify the endpoints after the client is installed.

Client credentials

Client credentials are a list of credentials the Module Server uses to log in to endpoint computers for installation of the Tanium Client. This list of credentials is tried in the defined order for each endpoint in the deployment.

Target endpoints

When you create and run a deployment, you can target endpoints by IP address or range, computer name, or labels from Tanium™ Discover.

Client health monitoring

After clients are installed, you can use Client Management to continuously monitor client health. Quickly identify outliers and issues by viewing aggregated information for clients on supported operating systems. Diagnose specific issues with Windows, Linux, and Mac clients by directly connecting and exploring individualized client health information.

Integration with other Tanium products

Discover

You can apply labels to the unmanaged interfaces that are identified with Discover, and then you can target endpoints using those labels.

Trends

Client Management features Trends boards that provide data visualization of Client Management concepts, including successful and failed deployments, and the versions of the Tanium Client that were deployed. The following panels are in the **Tanium Client Management** board:

- Tanium Client versions deployed
- Tanium Client versions deployed - latest
- Successful installations
- Deployment failures

For more information about how to import the Trends boards that are provided by Client Management, see [Tanium Trends User Guide: Importing the initial gallery](#).

Getting started

1. Install and configure Tanium Client Management. For more information, see [Installing Client Management on page 29](#).
2. Configure client configuration settings. These configurations define the properties of the clients that you want to install on the endpoint, including platform, client version, and the Tanium Server name. For more information, see [Configure client settings on page 34](#).
3. Configure credentials. These credentials specify the user names and passwords that are required to install the clients. The priority of credentials defines the order to try each user name and password combination. For more information, see [Configure client credentials on page 36](#).
4. Deploy Tanium Client. Specify settings for the deployment, including the configured client configuration and credentials settings. Target the endpoints on which you want to install the Tanium Client, schedule the deployment, and define the method you want to use to deploy. For more information, see [Configure a deployment on page 38](#).
5. Monitor deployment results. View the results of the deployment, and re-deploy if necessary. For more information, see [Run and monitor deployments on page 40](#).
6. Monitor client health. View the status of deployed clients over time and maintain them as necessary. For more information, see [Monitoring client health on page 43](#).

Client Management requirements

Review the requirements before you install and use Client Management.

Tanium dependencies

In addition to a license for Client Management, make sure that your environment meets the following requirements.

Component	Requirement
Tanium™ Core Platform	7.2 or later
Tanium™ Client	Client Management does not require a pre-existing installation of Tanium Client. Using Tanium™ Direct Connect to access detailed client health information requires Tanium Client 7.2.314.3211 or later.
Tanium products	<p>If you clicked Install with Recommended Configurations when you installed Client Management, the Tanium Server automatically installed all your licensed modules at the same time. Otherwise, you must manually install the modules that Client Management requires to function, as described under Tanium Console User Guide: Manage Tanium modules.</p> <p>The following modules are optional, but Client Management requires the given minimum versions to work with them:</p> <ul style="list-style-type: none">• (Optional) Tanium™ Discover 3.1 or later. With Discover, you can target endpoints based on Discover tags.• (Optional) Tanium™ Trends 2.4 or later. With Trends, you can view boards that provide data visualizations of client deployment information.• (Optional) Tanium Direct Connect 1.4.3 or later. With Direct Connect, you can connect to endpoints to access detailed client health information.

Tanium™ Module Server

Client Management is installed and runs as a service on the Module Server host computer. The impact on the Module Server is minimal and depends on usage.

Endpoints

For a list of supported operating systems for the Tanium Client, see [Tanium Client Guide: Host system requirements](#).

Supported operating systems

The following endpoint operating systems are supported with Client Management.

Operating System	Version
Microsoft Windows Server	2008 R2 with Service Pack 1 or later
Microsoft Windows Workstation	7 and later
macOS	Same as Tanium Client support. See Tanium Client User Guide: Host system requirements .
Linux	Same as Tanium Client support. See Tanium Client User Guide: Host system requirements . Note: Using Direct Connect to access detailed client health information on a CentOS client requires CentOS version 6.0 or later.
Solaris	Same as Tanium Client support. See Tanium Client User Guide: Host system requirements . Note: You cannot use Direct Connect to access detailed client health information with Solaris.
AIX	Same as Tanium Client support. See Tanium Client User Guide: Host system requirements . Note: You cannot use sing Direct Connect to access detailed client health information with AIX.

Account permissions

During client installation using Client Management, you must have an account configured with the appropriate permissions on each endpoint. You add credentials for these accounts during the deployment process. For more information, see [Configure client credentials on page 36](#). These accounts and permissions are necessary only during deployment, and they can be removed or changed after you successfully deploy clients.

Tip: To protect credentials that are used for client deployment, use one of the following methods:

- Use a temporary account that is removed after deployment.
- Disable or change the password for the account after client deployment is complete.

WINDOWS ENDPOINTS

On each Windows endpoint, you must have a local or Active Directory account configured that has the following abilities:

- Remotely connect to the endpoint and authenticate using SMB.
- Create folders in the `C:\Program Files (x86)\` directory for 64-bit Windows, or the `C:\Program Files\` directory for 32-bit Windows.
- Write and execute files in the `C:\Program Files (x86)\Tanium\` directory for 64-bit Windows, or the `C:\Program Files\Tanium\` directory for 32-bit Windows.

NON-WINDOWS ENDPOINTS

On each non-Windows endpoint, you must have an account configured that can remotely connect to the endpoint and authenticate using SSH. You must use *one* of the following options to configure a user with elevated privileges to perform installation:

- The root user
- A user that is listed in the `sudoers` file on each endpoint, to allow the account you are using for installation to use **sudo**

Host and network security requirements

Specific ports and processes are needed to run Client Management.

For information about preparing endpoints for remote installation, see [Prepare for deployment to Linux, macOS, or UNIX endpoints on page 32](#) and [Prepare for deployment to Windows endpoints on page 33](#).

Ports

The following ports are required for Client Management communication.

Component	Port	Direction	Purpose
Module Server (Windows)	22 135 139 445	Outbound	Communicate with endpoints during client installation RPC must be enabled from the module server
	17475	Inbound	Direct connection to endpoints for detailed client health information
Module Server (Non-Windows)	22 135 445	Outbound	Communicate with endpoints during client installation
	17475	Inbound	Direct connection to endpoints for detailed client health information
Zone Server	17486	Inbound	(Optional) Connections from endpoints for detailed client health information.
	17487 17488	Inbound (Module Server to Zone Server)	(Optional) Connection to Tanium zone proxy for direct connections to endpoints. This port only needs to be accessible from the internal network to the DMZ.
Endpoints (Windows)	17472	Inbound, Outbound	Communicate with Module Server during client installation
	135 445	Inbound	Communicate with Module Server during client installation
Endpoints (Non-Windows)	17472	Inbound, Outbound	Communicate with Module Server during client installation
	22	Inbound	Communicate with Module Server during client installation

Security exclusions

If security software is in use in the environment to monitor and block unknown host system processes, your security administrator must create exclusions to allow the Tanium processes to run without interference.

The `<Tanium Client>` variable refers to the Tanium Client installation path, which is configurable during client deployment. For default client installation paths, see [Tanium Client User Guide: Tanium Client installation paths](#).

The `<Tanium Module Server>` variable refers to the Tanium Module server installation path.

Note: Security exclusions for the Tanium Core Platform are also required to install Tanium clients using Client Management. For a list of these exclusions, see [Tanium Core Platform Deployment Reference Guide: Tanium Core Platform folders](#) and [Tanium Core Platform Deployment Reference Guide: Tanium Core Platform system processes](#).

Table 1: Client Management security exclusions

Target Device	Notes	Process
Module Server		"<Tanium Module Server>\services\client-management-service\node.exe" service.js
		<Tanium Module Server>\services\twsm-v1\twsm.exe

Target Device	Notes	Process
Windows x86 endpoints	During client installation	\Program Files\Tanium\TaniumClientBootstrap.exe
	During client installation	\Program Files\Tanium\SetupClient.exe
	During client installation	<Tanium Client>\SetupClient.exe
		<Tanium Client>\TaniumClientExtensions.dll
		<Tanium Client>\TaniumClientExtensions.dll.sig
		<Tanium Client>\extensions\TaniumDEC.dll
		<Tanium Client>\extensions\TaniumDEC.dll.sig
		<Tanium Client>\TaniumCX.exe
Windows x64 endpoints	During client installation	\Program Files (x86)\Tanium\TaniumClientBootstrap.exe
	During client installation	\Program Files (x86)\Tanium\SetupClient.exe
	During client installation	<Tanium Client>\SetupClient.exe
		<Tanium Client>\TaniumClientExtensions.dll
		<Tanium Client>\TaniumClientExtensions.dll.sig
		<Tanium Client>\extensions\TaniumDEC.dll
		<Tanium Client>\extensions\TaniumDEC.dll.sig
		<Tanium Client>\TaniumCX.exe

Target Device	Notes	Process
macOS endpoints	During client installation	/Library/Tanium/TaniumClientBootstrap
	During client installation	/Library/Tanium/SetupClient
	During client installation	<Tanium Client>/SetupClient
		<Tanium Client>/libTaniumClientExtensions.dylib
		<Tanium Client>/libTaniumClientExtensions.dylib.sig
		<Tanium Client>/extensions/libTaniumDEC.dylib
		<Tanium Client>/extensions/libTaniumDEC.dylib.sig
		<Tanium Client>/TaniumCX
Linux endpoints	During client installation	/opt/Tanium/TaniumClientBootstrap
	During client installation	/opt/Tanium/SetupClient
	During client installation	<Tanium Client>/SetupClient
		<Tanium Client>/libTaniumClientExtensions.so
		<Tanium Client>/libTaniumClientExtensions.so.sig
		<Tanium Client>/extensions/libTaniumDEC.so
		<Tanium Client>/extensions/libTaniumDEC.so.sig
		<Tanium Client>/TaniumCX

Target Device	Notes	Process
Solaris and AIX endpoints	During client installation	/opt/Tanium/TaniumClientBootstrap
	During client installation	/opt/Tanium/SetupClient
	During client installation	<Tanium Client>/SetupClient

Internet URLs

If security software is deployed in the environment to monitor and block unknown URLs, your security administrator might need to add the following URL to the whitelist.

- <https://content.tanium.com>

User role requirements

Table 2: Client Management user role permissions

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Show Clientmanagement¹ View the Client Management workbench	✓ ²	✓ ²	✓ ²	✓	✓	✓ ²

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Client-management Configurations Read Read client and deployment configurations	✓ ²	✓	✗	✗	✗	✓
Client-management Configurations Write Create and modify client and deployment configurations	✓	✗	✗	✗	✗	✗

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Client-management Credentials Read Read credentials list, but not view associated passwords or key data	✓ ²	✓	✗	✗	✗	✓
Client-management Credentials Write Create and modify credentials lists	✓	✗	✗	✗	✗	✗

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Client-management Credentials View View passwords or key data for credentials lists	✘	✘	✘	✘	✘	✘
Client-management Deployments Read View data about client deployments	✔ ²	✔ ²	✘	✘	✘	✔

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Client-management Deployments Write Create deployments of Tanium Client to unmanaged endpoints	✔	✔	✘	✘	✘	✘
Client-management Direct Connect Connect to an endpoint using Direct Connect and read data from that endpoint	✔	✘	✘	✘	✔	✘

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Client-management Settings Write Write access to global settings in the Client Management module	✓	✗	✓	✗	✗	✗
Client-management Read Audit Log Read audit log with API	✓	✗	✗	✓	✗	✗
Client-management Use API Write access to global settings in the Client Management module	✓	✗	✓	✗	✗	✗

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Direct Connect Session Read Allows users to view endpoint connections	✓ ²	✗	✗	✗	✓ ²	✗
Direct Connect Session Write Allows users to create and manage endpoint connections	✓ ²	✗	✗	✗	✓ ²	✗
Trends Data Read³ Run data queries against sources	✓	✓	✗	✗	✗	✓

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Trends API Board Read³ View boards, sections, and panels for specified content sets	✓	✓	✗	✗	✗	✓
Trends API Board Write³ Create, edit, delete, and configure boards, sections, and panels for specified content sets	✓	✗	✗	✗	✗	✗
Trends API Source Read³ View and list sources for specified content sets	✓	✓	✗	✗	✗	✓

Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Trends API Source Write³ Create, edit, and delete sources for specified content sets	✔	✘	✘	✘	✘	✘

¹ To install Client Management, you must have the reserved role of Administrator.

² Denotes a provided permission.

³ Denotes a permission that applies to the Reserved content set.

Table 3: Provided Client Management Micro Admin and Advanced user role permissions

Permission	Role Type	Content Set for Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Read System Status	Micro Admin		✔	✘	✘	✘	✔	✘
Read Sensor	Advanced	Tanium Client Management	✔	✔	✔	✔	✔	✔

Permission	Role Type	Content Set for Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Read Sensor	Advanced	Reserved	✓	✓	✓	✓	✓	✓
Read Sensor	Advanced	Base	✓	✓	✓	✓	✓	✓
Read Sensor	Advanced	Client Extensions	✓	✓	✓	✓	✓	✓
Read Sensor	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Read Action	Advanced	Reserved	✓	✗	✗	✗	✓	✗
Read Action	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Write Action	Advanced	Reserved	✓	✗	✗	✗	✓	✗
Write Action	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Execute Plugin	Advanced	Tanium Client Management	✓	✓	✓	✓	✓	✓
Execute Plugin	Advanced	Reserved	✓	✓	✓	✗	✗	✓
Read Package	Advanced	Reserved	✓	✗	✗	✗	✓	✗
Read Package	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Write Package	Advanced	Reserved	✓	✗	✗	✗	✓	✗

Permission	Role Type	Content Set for Permission	Client Management Administrator	Client Management User	Client Management API User	Client Management Auditor	Client Management Operator	Client Management Read-Only User
Write Package	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Read Saved Question	Advanced	Tanium Client Management	✓	✓	✓	✓	✓	✓
Read Saved Question	Advanced	Reserved	✓	✓	✓	✗	✓	✓
Read Saved Question	Advanced	Direct Connect	✓	✗	✗	✗	✓	✗
Read Filter Group	Advanced	Tanium Client Management	✓	✓	✓	✓	✓	✓
Read Filter Group	Advanced	Reserved	✓	✓	✓	✓	✓	✓
Read Filter Group	Advanced	Default Filter Groups	✓	✓	✓	✓	✓	✓

Table 4: Optional roles for Client Management

Role	Enables
Discover Read Only User	For service account: Deploy to endpoints based on Discover labels

For more information and descriptions of content sets and permissions, see [Tanium Core Platform User Guide: Managing roles](#).

Installing Client Management

Use the **Tanium Solutions** page to install Client Management and choose either automatic or manual configuration:

- **Automatic configuration with default settings** (Tanium Core Platform 7.4.2 or later only): Client Management is installed with any required dependencies and other selected products. After installation, the Tanium Server automatically configures the recommended default settings. This option is the best practice for most deployments. For more information about the automatic configuration for Client Management, see [Import and configure Client Management with default settings on page 29](#).
- **Manual configuration with custom settings:** After installing Client Management, you must manually configure required settings. Select this option only if Client Management requires settings that differ from the recommended default settings. For more information, see [Import and configure Client Management with custom settings on page 29](#).

Before you begin

- Read the [release notes](#).
- Review the [Client Management requirements on page 10](#).
- Assign the correct roles to users for Client Management. Review the [User role requirements on page 17](#). To import the Client Management solution, you must be assigned the Administrator reserved role.

Import and configure Client Management with default settings

When you import Client Management with automatic configuration, the Client Management service account is set to the account that you used to import the module.

To import Client Management and configure default settings, be sure to select the **Apply Tanium recommended configurations** check box while performing the steps in [Tanium Console User Guide: Manage Tanium modules](#). After the import, verify that the correct version is installed: see [Installing Client Management on page 29](#).

Import and configure Client Management with custom settings

To import Client Management without automatically configuring default settings, follow the steps in [Tanium Console User Guide: Manage Tanium content packs](#). After the import,

verify that the correct version is installed: see [Installing Client Management on page 29](#).

Configure service account

The service account is a user that runs several background processes for Client Management. This user requires the following roles and access:

- **Content Administrator** and **Tanium Client Administrator**, or **Tanium Administrator**
- (Optional) **Discover Read Only User** role, to deploy to endpoints based on labels created in Tanium Discover

For more information about Client Management permissions, see [User role requirements on page 17](#).

1. From the Main menu, click **Tanium Services > Tanium Client Management** to open the Client Management **Home** page.
2. Click Settings  and open the **Service Account** tab.
3. Update the service account settings and click **Save**.

Verify installation

To verify that Client Management is installed, go to the **Tanium Solutions** page and check the installed version.

(Tanium 7.2.x, 7.3.x only) Upload Tanium public key

If you are using Tanium Server 7.2.x or 7.3.x, upload the Tanium public key. This public key enables the connection between the clients you are installing and the Tanium Server. This configuration occurs automatically with Tanium Server 7.4 and later.

1. From the Client Management home page, click Settings .
2. Click **Choose File** and select the `tanium.pub` file for your Tanium Server. The `tanium.pub` file is in the top-level installation directory for the Tanium Server.
3. Click **Upload**.

Add client installation files for air-gapped environments

If you cannot enable communication between your Tanium Module Server and `content.tanium.com`, contact your TAM to configure client installers on the Tanium Module Server.

What to do next

See [Getting started on page 9](#) for more information about using Client Management.

Deploying Tanium Client

To deploy Tanium Client to unmanaged endpoints, configure your endpoints to accept connections from the Module Server. Create sets of client settings and credentials to define the types of clients to deploy and the information that is needed to log into the endpoints to perform the installations. Finally, use these configurations to create a deployment that targets a specific set of endpoints.

IMPORTANT: You can only install on endpoints that do not have a Tanium Client already installed. To upgrade the Tanium Client, see [Tanium Client User Guide: Upgrading Tanium Clients](#).

Note: When you use Client Management to deploy the Tanium Client to endpoints, Client Management also installs Client Management tools on the endpoints to provide client health information. For more information, see [Monitoring client health on page 43](#).

Plan deployment targeting

You can deploy the Tanium Client to a single IP, computer name, IP or CIDR range, or a Discover label.

If you want to deploy to unmanaged interfaces that get defined in Discover, you can create a label and use the label as a deployment target. For example, you create a `New Computers` label with the condition: `First Seen in the last 30 minutes AND Computer Id = "0"`. For more information about creating labels in Discover, see [Tanium Discover User Guide: Labels](#).

Prepare for deployment to Linux, macOS, or UNIX endpoints

1. Configure password-based or SSH key-based authentication based on what the endpoints expect.

For all Linux distributions, macOS, and UNIX, use one of the following options to configure a user with elevated privileges to perform installation:

- The root user on each endpoint
- A user that is listed in the sudoers file on each endpoint, to allow the account you are using for installation to use **sudo**

Amazon Linux requires key-based authentication. On the endpoint, be sure to enable SSH key-based authentication and enable `NOPASSWD` in the sudoers file for the admin user account. Add this user name and password to the credentials list. This configuration ensures that the key, and not a password, is used to elevate the admin permissions of the user so that the user can install the Tanium Client and start the service.

Other distributions or your specific environment might have different authentication requirements.

2. Allow traffic from the Module Server to endpoints on TCP port 22 (SSH port, configurable). For more information, see [Host and network security requirements on page 12](#)
3. Configure any host-based firewalls or other security tools on the endpoint that might interfere with a remote installation that is initiated through SSH. For more information, see [Host and network security requirements on page 12](#).
4. If you use the root account to install, make sure the `sshd_config` allows root login.
5. Verify that you can log in to the remote system with SSH, using the same credentials that you will use for the Tanium Client deployment.

Tip: To protect credentials that are used for client deployment, use one of the following methods:

- Use a temporary account that is removed after deployment.
- Disable or change the password for the account after client deployment is complete.

Prepare for deployment to Windows endpoints

1. Enable Windows file-and-print sharing and remote procedure calls (RPCs) on the target endpoints. Enabling these settings is required only for installation. You can disable the sharing and RPCs after the installation.
2. Configure any host-based firewalls or other security tools on the endpoint that might interfere with a remote installation initiated through RPC. For more information, see [Host and network security requirements on page 12](#).

3. Allow TCP traffic on ports 135 and 445 from the Tanium Module Server host computer to the endpoints on which you want to deploy the Tanium Client. For more information, see [Host and network security requirements on page 12](#).
4. Verify that you can log in to the remote system with PSEXEC or WMIC command line utilities with the same credentials that you will use for the Tanium Client deployment. For example:

```
psexec \\192.168.1.130 -u Administrator cmd /c dir  
C:\Users\Administrator\Documents  
wmic /node:"192.168.1.130" /user:"Administrator" useraccount list brief
```

Tip: To protect credentials that are used for client deployment, use one of the following methods:

- Use a temporary account that is removed after deployment.
- Disable or change the password for the account after client deployment is complete.

Configure client settings

Client settings define the Tanium Server, platforms, and installation directories for your client deployment. You can configure multiple client settings to deploy to different types of environments.

1. From the Client Management menu, click **Client Settings**, and then click **Create**.
2. Specify a descriptive name for the client settings.

3. Specify the IP address or fully qualified domain name of the Tanium Server from which you want to perform the deployment.

Create Client Settings

Configure the Tanium Client platforms and versions to install on endpoints and the Tanium Server that will perform the installation.

* Required

Client Settings Name *

Tanium Server Names *

Comma-separated list of fully qualified domain names or IP addresses

Client Version

Client Platforms *

Windows × Linux ×

The following operating systems are not supported for the selected version: debian6-x64, debian6-x86, opensuse11-x64, opensuse11-x86

Installation Directory on Windows

Installation Directory on Non Windows

Log Level ⓘ

Log verbosity level for endpoints

Client Port

Client Settings

Add Client Setting

Client Tags

Add Client Tag

Save Cancel

4. Select the **Client Version** to install.

5. Select the **Client Platforms** of the endpoints to which you are installing Tanium Client. You can leave the installation directories as their default values, or specify custom installation directories.
6. Leave the default installation directories, or enter a custom **Installation Directory on Windows** or **Installation Directory on Non Windows**.

Note: You cannot customize the installation directory on macOS. The fixed installation directory for macOS is `/Library/Tanium/TaniumClient`.

7. Enter a **Log Level**.

The following decimal values are best practices for specific use cases:

- **0**: Disable logging. This is the best practice value for clients installed on sensitive endpoints or virtual desktop infrastructure (VDI) endpoints.
- **1**: This is the best practice value during normal operation.
- **41**: This is the best practice value during troubleshooting.
- **91** or higher: Enable the most detailed log levels for short periods of time only.

8. Leave the default **Client Port**, or enter a custom port.
9. To change a default client settings, click **Add Client Setting**, and then enter a **Key** and **Value**. For information about specific client settings, see [Tanium Client User Guide: Tanium Client settings](#).
10. To add a custom tag to the client during deployment, click **Add Client Tag** and enter a tag name. The `InstalledByTCM` tag is included by default so that you can later easily target clients that were installed using Client Management.

Note: Do not include spaces in a tag name.

11. Click **Save**.

Tip: To download an installer bundle associated with a set of client settings, click Download Bundle  in the **Actions** column.

Configure client credentials

Client credentials are a list of user name and password combinations for the target endpoints on which you want to install Tanium Client.

1. From the Client Management menu, click **Credentials**. Click **Create**.
2. Specify a name for the credentials list, and a set of user names and passwords to try for each operating system type. On macOS and Linux endpoints, you can also specify a key or keyphrase.

Create Credentials

Configure a list of user name and password combinations for the target endpoints.

* Required

Name *

Windows Credentials

[+ Add](#)

All Other Credentials (Mac OSX, Linux)

[- key](#) [- keyphrase](#)

Key

Keyphrase

[+ Add](#)

[Save](#) [Cancel](#)

3. Click **Save**.

Configure a deployment

1. From the Client Management menu, click **Deployments**, and then click **Create**.
2. Specify a descriptive name for the deployment, and select the client configuration and credentials that you configured.
3. Configure targeting. You can target endpoints by a single IP, computer name, IP or CIDR range, or Discover label. For information about configuring Discover labels, see [Tanium Discover User Guide: Labels](#).

4. Tune the settings in the **Method** section as needed.

Create Deployment

Select a configuration and client configuration, and configure the deployment of Tanium Client

* Required

Deployment Name *

Description

Client Configuration *

Credentials List *

Targeting

Method

SSH Port *

Retry Delay *

Delay between connection retries (in seconds)

Retry Limit *

Max connection attempts per IP

Install Delay *

Delay between install attempts (in seconds)

Install Limit *

Max concurrent installs

5. Click **Save** to save the deployment without running, or **Save and Deploy** to immediately deploy.

Run and monitor deployments

From the Client Management menu, click **Deployments**. In the **Name** column, click the name of a deployment.

To run the deployment, click Start ▶.

Note: If you re-run a deployment that has previously installed the client on some endpoints, those endpoints then report the Install Status: `ERROR_EXISTING_INSTALL`. The previously installed client remains in place. To upgrade the Tanium Client, see [Tanium Client User Guide: Upgrading Tanium Clients](#).

You can then view the status of the deployment, including viewing a list of the targeted endpoints.

Tanium > Tanium Client Management > Deployments >

WindowsDeploy

Status	Complete	Running	Failed	No Connection	Existing Client	Total Endpoints
completed	3	-	-	-	-	3

Deployment Settings

Targeting

IP Address: 10.70.145.134,10.70.145.198,10.70.145.207

Settings

Client	WindowsSettings	SSH Ports:	22
Configuration:	WindowsSettings	Simultaneous	5
Credentials:	WindowsCredentials	Installs:	60
Deployment ID:	3	Delay Between Installs:	seconds
Last Modified:	5/28/2020, 11:54:56 AM	Number Of Retries:	5
Created:	5/28/2020, 11:54:56 AM	Delay Between Retries:	60 seconds

Endpoint Details

Items: 3 [Advanced Filters](#)

All Complete Failed Running Existing Client No Connection Filter logs and details...

Address	Install Status	Status Details
10.70.145.134	COMPLETE	Installation bootstrap service result file indicates completion.
10.70.145.198	COMPLETE	Installation bootstrap service result file indicates completion.
10.70.145.207	COMPLETE	Installation bootstrap service result file indicates completion.

Deployment steps

When you start a deployment, the Module Server takes the following actions to install the Tanium Client:

1. Pings the targeted endpoints to verify they are online.
2. Detects the operating system of the endpoints that respond to the ping.
3. Tries the credentials in the defined credentials list to log into the endpoint for installation.

4. Checks for the space required on the endpoint as specified in the client settings.
5. Copies the Tanium public key file for the Tanium Server to the endpoint.
6. Installs Tanium Client on the endpoint. The version and installation location are defined in the client configuration for the deployment.
7. Displays the deployment status.

Deployment status

Each successful deployment reports a status of `COMPLETE` in the **Install Status** column.

Filter the endpoints by clicking the status buttons in the grid, or enter filter text in the **Filter logs and details** box.

For more information about other status messages and troubleshooting deployments, see [Troubleshoot deployments on page 50](#).

Verify client installation

To verify the installation on an endpoint has completed:

1. From Interact, enter a question in the **Ask a Question** field to verify that the endpoints respond to the following query: `Get Computer Name and Operating System and Tanium Client Version and Tanium Server Name from all machines`
2. Review the **Question Results** grid to verify that all endpoints where you deployed Tanium Client software are reporting.
3. (Optional) From the main menu, go to the **Administration > System Status** page to review recent client registration details.

Monitoring client health

Review health information about deployed clients.

View a summary of client health information

From the **Client Management** menu, go to **Client Health**.

The **Deployment** tab displays a summary of client deployment information, such as client versions, health check failures, operating systems, installed client extensions, and Python

runtime versions.

Deployment
Settings

Deployment

Computer Group: Select...

▾ Clients

Client Version

Version	Count ↓
6.0.314.1568	912
7.4.2.2033	3
7.2.314.3518	2

Health Failures

Domain	Failure	Count
performance	tsdb is disabled and not running	6
performance	database is not initialized	5
performance	tsdb is	4

OS Platforms

Platform	Count ↓
Windows	746
Linux	67
Mac	64
AIX	20
Solaris	20

▾ Components

Client Extensions

Domain	Version	Count ↓
core	2.2.0.1114	912
threatresponse	0.1.28	912
recorder	2.0.1.4067	912
performance	1.4.18	457
performance	1.3.4	455
dec	1.3.13	304
dec	1.4.0	304
dec	1.5.0	304

Python Runtimes

Component	Version	Count ↓
3.8 Python Interpreter Version	3.8.1	947
2.7 sqlite version	3.31.1	947
3.8 sqlite version	3.31.1	947
2.7 Core Python Version	1.3.0.44	945
2.7 Python Interpreter Version	2.7.15	945
Sensor Python Version	2.7	943
3.8 Core Python Version	1.3.0.44	942

© 2020 Tanium Inc. All Rights Reserved

Page 44

The **Settings** tab displays a summary of client settings, such as log verbosity level, server name, server port, and various component information. This overview can help identify settings that have been changed from defaults.

Deployment **Settings**

Settings Computer Group: Select...

This page displays any settings that have been applied to your endpoints. Any values currently in their default state are not displayed.

Client

▼ LogVerbosityLevel

Setting Value	Count
1	3
31	156
21	157
11	158
71	157
41	158
91	158

▼ ServerName

Setting Value	Count
192.168.56.80	942
10.70.145.96	5

▼ ServerPort

Setting Value	Count
17472	947


On either tab, you can select a **Computer Group** to filter the summary information.

To further investigate a data set using the associated question results, click View question results in Interact . For more information about working with question results, see [Tanium Interact User Guide: Managing question results](#).

View detailed client health information for an endpoint

You can directly connect to a Windows, Linux, or macOS endpoint to view more detailed client health information.

1. From the Client Management menu, go to **Client Health**.
2. In the **Direct Connect** search box, enter all or part of an IP address or a computer name.
Matching results are displayed after the search completes.
3. From the search results, click the computer name to connect to the endpoint.



Note: If the connection to the endpoint times out, click **Reconnect** to reestablish the connection.

View detailed status information

Click the **Status** tab to view detailed client status information about the connected endpoint, such as the computer ID, the first and last client installation time stamps, the installed client version, client and peer address information, and client extension

information, including any health check failures.

Tanium > Tanium Client Management > **Disconnect** Status ✔ **Connected**

WIN-10-X64

Status Configuration Logs Actions

Client

ComputerID	1939980191	BackPeerAddress	NoAddress_NoAddress
FirstInstall	28/05/2020 8:15:56	BackPreviousPeerAddress	512:49909:10.70.145.134_512:0:10.70.145.134
LastInstall	28/05/2020 8:15:56	ClientAddress	512:17472:10.70.145.95_512:0:10.70.145.95
RegistrationCount	145	LastRegistrationTime	2020-05-28T18:29:20
ServerName	10.70.145.96	NeighborhoodList	512:17472:10.70.145.95_512:0:10.70.145.95, 512:17472:10.70.145.134_512:0:10.70.145.134, 512:17472:10.70.145.198_512:0:10.70.145.198
ServerPort	17472	PeerAddress	512:17472:10.70.145.134_512:0:10.70.145.134
Server_TLSMode	1	PreviousPeerAddress	NoAddress_NoAddress
Version	7.4.2.2033		

Client Extensions

Component ^①	Name ^②	Value
core	version	2.2.0.1126
dec	connection_state	connected
dec	version	1.3.21
support	version	1.3.6

View detailed client settings information

Click the **Configuration** tab to view detailed information about client settings for the connected endpoint, such as log verbosity level, server name, server port, and various

settings for client extensions.

Tanium > Tanium Client Management > **Disconnect** Status ✔ **Connected**

WIN-10-X64

Status **Configuration** Logs Actions

▾ Client


Name	Value
LogVerbosityLevel	1
ServerName	10.70.145.96
ServerPort	17472
Server_TLSMode	1

▾ Client Extensions

Comp...	Name	Description	Default Value	Current Value
core	CpuThrottleCalculateTotalSystem	Calculate CPU utilization as a function of total system capacity, not a single CPU	1	(default)
core	CpuThrottleMaximumSampleMillise	Maximum time (ms) between samples for the CPU throttle check	5000	(default)
core	CpuThrottleMinimumSampleMillise	Minimum time (ms) between samples for the CPU throttle check	250	(default)
core	CpuThrottleTargetPercent	Target maximum CPU (% total system capacity) for the extensions process	5	(default)

View logs from the connected client

To view logs from the connected client, click the **Logs** tab, and select a log to view.



For information about reviewing logs for troubleshooting, see [Tanium Client User Guide: Troubleshooting](#).

View action logs from the connected client

To view action logs from the connected client, click the **Actions** tab, and select a previously run action for which you want to view the log.

For information about reviewing action logs for troubleshooting, see [Tanium Client User Guide: Action_logs](#).

Disconnect and return to summary information

To disconnect from the endpoint and return to the client health summary, click **Disconnect**.

Troubleshooting Client Management

To send information to Tanium for troubleshooting, collect logs and other relevant information.

Collect logs

The information is saved as a ZIP file that you can download with your browser.

1. From the Client Management home page, click Help , then the **Troubleshooting** tab.
2. Click **Download Debug Package**.
A `tanium-client-management-support.zip` file downloads to the local download directory.
3. Attach the ZIP file to your Tanium Support case form or send it to your Technical Account Manager (TAM).

Tanium Client Management maintains logging information in the `client-management.log` file in the `\Program Files\Tanium\Tanium Module Server\services\client-management-files` directory.

Download deployment information

You can download a JSON file that includes deployment settings and endpoint details for a deployment.

1. From the Client Management menu, click **Deployments**.
2. In the **Name** column, click the name of a deployment.
3. Click Download  to download the JSON file.

Troubleshoot deployments

Problem: A new deployment instantly switches to the Completed status with no attempted deployments to endpoints

The Module Server is having trouble downloading the client binaries.

SOLUTION

Check the TDownloader log for download errors. For information about where to find this log, see [Tanium Core Platform Deployment Reference Guide: TDownloader logs](#).

Problem: Endpoint Install Status = ERROR_EXISTING_INSTALL

Log messages for the deployment contain the following message:

```
Existing Tanium Client installation detected.
```

SOLUTION

The client might have been successfully installed during a previous deployment. If you are attempting to upgrade the client, follow the steps in [Tanium Client User Guide: Upgrading Tanium Clients](#).

Problem: Endpoint Install Status = ERROR_ACQUIRE_LOGS_FAIL

Log messages for the deployment contain the following message:

```
Deployment Result Generated: Necessary file(s) missing on disk: C:\Program Files\Tanium\Tanium Module Server\services\client-management-files\deployment-runner-data\bc6bf6fd-0388-4f2d-9120-860cac75e8d4\tanium.pub
```

SOLUTION

Upload the `tanium.pub` file. See [\(Tanium 7.2.x, 7.3.x only\) Upload Tanium public key on page 30](#).

Problem: Endpoint Install Status = ERROR_CONNECTION_FAIL

Log messages for the deployment contain the following message:

```
Deployment Result Generated: All 1 connection attempt(s) resulted in no response from the target.
```

SOLUTION

- Check the user name provided with the credentials. Credentials must be active and not disabled. Check that the domain is added correctly, for example:
`domain\username` for a domain account, or `username` for a local endpoint account.
- Check the password provided with the credentials to ensure it is not disabled or expired.
- Check both the target endpoint firewall and network device firewalls. The Module Server might be blocked from initiating a connection to the target endpoint by a firewall. SMB ports on 139 and 445 must be open. SSH port 22 must be open. Use the following testing techniques to check the ports:
 - Test Network connections:
 - Windows PowerShell: `Test-NetConnection -computer ip_address -port port_number`
 - Linux: `telnet`, `nc` / `netcat`
 - Check TanOS network status: See [Tanium Appliance Deployment Guide: Support menu](#).
- (Windows endpoints) If the client is non-domain joined, you must edit the Windows registry to allow remote installations.

In most Active Directory environments, admin shares are already available. For standalone machines that have not joined the domain, you might have to enable admin shares so that a user can reach `c$` with sufficient permissions. In Windows 7 and 8 machines, enable the admin shares of a standalone machine by adding the following registry key and restarting the computer:

```
Hive: HKEY_LOCAL_MACHINE
Key: Software\Microsoft\Windows\CurrentVersion\Policies\System
Name: LocalAccountTokenFilterPolicy
Data Type: REG_DWORD
Value: 1
```

IMPORTANT: Admin shares are not available in Home editions of Windows operating systems.

Problem: Endpoint Install Status = ERROR_CONNECTION_FAIL

Log messages for the deployment contain the following message:

```
Command resulted in error: Error: Connection to 'SSH Client for '192.168.24.11'' was not established
```

SOLUTION

- Verify the client configuration and deployment settings. You might be targeting a Windows endpoint with a deployment while only using SSH as a connection method.
- Verify that the targeted Linux endpoint has SSH enabled and is configured on port 22.
- Check the user name provided with the credentials. Credentials must be active and not disabled. Check that the domain is added correctly, for example: `domain\username` for a domain account, or `username` for a local endpoint account.
- Check the password provided with the credentials to ensure it is not disabled or expired.

Problem: Endpoint Install Status = ERROR_ACQUIRE_LOGS_FAIL

Log messages for the deployment contain the following message:

```
SMB 'mkdir' command exited with exit code 1.
```

SOLUTION

Verify that you are not trying to deploy to an endpoint that already has the Tanium Client installed. The endpoint could have a Tanium Client that was not fully removed, or a Tanium Client installation that points to a different Tanium Server.

Uninstall Client Management

1. From the Main menu, click **Tanium Solutions**.
2. In the **Tanium Content** section, select the **Client Management** row.
3. Click **Uninstall Solution**. Click **Uninstall** to complete the process.